

# The `xgalley` package

## Galley\*

The L<sup>A</sup>T<sub>E</sub>X3 Project<sup>†</sup>

Released 2012/12/17

## 1 Introduction

In L<sup>A</sup>T<sub>E</sub>X3 terminology a galley is a rectangular area which receives text and other material filling it from top. The vertically extend of a galley is normally not restricted: instead certain chunks are taken off the top of an already partially filled galley to form columns or similar areas on a page. This process is typically asynchronous but there are ways to control or change its behaviour.

Examples for galleys are “the main galley”, where the continuous document data gets formatted into and from which columns and pages are constructed, and “vertical box galleys”, such as the body of a minipage environment. The latter galleys are typically not split after formatting, though there can be exceptions.

## 2 Formatting layers

The present module is mainly concerned with the formatting of text in galleys. The mechanism by which this is achieved uses four (somewhat) distinct layers, some of which can be addressed using the templates provided here.

### 2.1 Layer one: external dimensions

The bottom layer of the system is the external dimensions of the galley. Normally only the horizontal dimension is fixed externally, while the vertical (filling) dimension is unspecified. The external dimensions are fixed when starting a new galley, and are therefore not modifiable within the galley.

There are no templates for setting this layer directly, although the external values are influenced by other parts of the system (for example when creating minipage environments).

---

\*This file describes v4373, last revised 2012/12/17.

†E-mail: [latex-team@latex-project.org](mailto:latex-team@latex-project.org)

## 2.2 Layer two: internal dimensions

The second layer is the internal dimensions of the galley: the *measure* used for paragraph text and the position of the paragraph relative to the edges of the galley.

This layer is normally accessed by higher-level templates *via* the object type **measure**. Changes made using level two templates will often extend for large parts of a document (up to and including the entire document).

## 2.3 Layer three: paragraph shape

The third layer defines the paragraph shape within the measure as provided by the second layer. In the absence of any specification for that layer the paragraph shape used will be that of a rectangular area of the width of the current measure.

There are some restrictions imposed on the shape of a paragraph by the underlying TeX mechanisms. For example, cut out sections in paragraphs can be specified from the top of the paragraph but not from the bottom.

## 2.4 Layer four: formatting inside the paragraph

The forth layer deals with the paragraph formatting aspects such as hyphenation and justification within the paragraph (this is sometimes referred to as “h&j” or “hj”).

# 3 Templates

## 3.1 Layer two: internal dimensions

### 3.2 The object type ‘measure’

**Arg:**

#### Semantics:

Sets the width available to typeset material within the galley. The *<left margin>* and *<right margin>* values are used in the adjustment to over-ride any given in the template. Depending upon the template in use, the margins may be absolute (relative only to the edges of the galley) or relative (taking account of **measure** adjustments already made). The template applies to the galley from the point of us forward, unless over-ridden by another use of the **measure** object type.

## 3.3 The template ‘absolute’ (object type **measure**)

#### Attributes:

**left-margin (length)** The distance from the left edge of the galley to the left edge of the area for typeset material. A negative value will cause the typeset material to extend beyond the edge of the galley. Default: 0 pt

**right-margin (length)** The distance from the right edge of the galley to the right edge of the area for typeset material. A negative value will cause the typeset material to extend beyond the edge of the galley. Default: 0 pt

**Semantics & Comments:**

This template sets up the typesetting area such that typeset material runs from **left-margin** away from the left edge of the galley to **right-margin** away from the right edge of the galley. Both of these distances are absolute, *i.e.* no account is taken of previous **measure** settings. Either on or both values may be negative, in which case the typeset material will protrude outside of the edges of the galley.

### 3.4 The template ‘relative’ (object type measure)

**Attributes:**

**left-margin (length)** The distance from the previous left margin of the typeset material within the galley to the new position of the left margin. A negative value will cause the new margin to be “outside” of the previous one, and *may* cause the typeset material to protrude outside of the edge of the galley. Default: 0 pt

**right-margin (length)** The distance from the previous right margin of the typeset material within the galley to the new position of the right margin. A negative value will cause the new margin to be “outside” of the previous one, and *may* cause the typeset material to protrude outside of the edge of the galley. Default: 0 pt

**Semantics & Comments:**

This template sets up the typesetting area such that it has margins **left-margin** and **right-margin** within those previously set. For a galley within no previous margins, this will result in margins relative to the edges of the galley. Within a galley in which the **measure** has already been set, using the **relative** template will indent the typeset material relative to the existing margins. Either on or both values may be negative, in which case the typeset material may protrude outside of the edges of the galley.

### 3.5 Layer three: paragraph shape

### 3.6 The object type ‘parshape’

**Arg:**

#### **Semantics:**

Template of this type define any shaping of the paragraph within the current measure of the galley. Thus they are used to generate “special” paragraph shapes, for example placing a cutout in one side of the paragraph. Typically, `parshape` templates will apply in a limited sense (to a single paragraph or a defined number of lines). However, `parshape` templates may also apply in an “ongoing” manner.

Note that `parshape` templates do not alter any first-line indent for paragraphs (or any other “in paragraph” setting). Instead, they define a shape inside which the paragraph material will be placed.

### **3.7 The template ‘hang’ (object type parshape)**

#### **Attributes:**

**indent (length)** The hanging indent from either the left- or right-hand margin (as determined by `on-left-side`). Default: 0 pt

**on-left-side (boolean)** If `true`, causes the hanging indent to be on the left-hand side of the paragraph. Default: true

**lines (integer)** The number of lines of full width before hanging begins. Default: 1

#### **Semantics & Comments:**

Sets the paragraph shape such that the after a number of full-width lines, specified by `lines`, the paragraph is indented by the `indent` from a margin. If `on-left-side` is `true` this indent will be from the left-hand margin, otherwise it will be from the right. In either case, the indent is relative to the edge of the current `measure` and may be negative (in which case an outdent will result). This template type applies only to a single paragraph.

### **3.8 The template ‘initial’ (object type parshape)**

#### **Attributes:**

**indent (length)** The indent for the initial lines from either the left- or right-hand margin (as determined by `on-left-side`). Default: 0 pt

**on-left-side (boolean)** If `true`, causes the indent to be on the left-hand side of the paragraph. Default: true

**lines (integer)** The number of lines of indented lines before full-width line begins. Default: 2

#### **Semantics & Comments:**

Sets the paragraph shape such that the first `lines` lines are indented by the `indent` given, before lines of full width begin. If `on-left-side` is `true` this indent will be from the left-hand margin, otherwise it will be from the right. In either case, the indent is relative to the edge of the current `measure` and may be negative (in which case an `outdent` will result). This template type applies only to a single paragraph.

### **3.9 The template ‘std’ (object type parshape)**

#### **Attributes:**

`()`

#### **Semantics & Comments:**

Sets a rectangular paragraph shape which occupies the full width specified by the `measure`. It is therefore intended as a “do nothing” template for use where a paragraph shape is required but where no special formatting is needed. This template type applies only to a single paragraph.

### **3.10 Layer four: formatting inside the paragraph**

### **3.11 The object type ‘hyphenation’**

#### **Arg:**

#### **Semantics:**

Controls whether hyphenation is attempted within the current galley. This object type may also alter the degree to which hyphenation is encouraged by manipulating the underlying T<sub>E</sub>X parameters. This object type applies to the galley from the point of use forward.

### **3.12 The template ‘std’ (object type hyphenation)**

#### **Attributes:**

**enable (boolean)** Switches all hyphenation on or off. Default: true

**enable-upper-case (boolean)** Switches hyphenation on or off for words beginning with upper case letters. Default: true

**penalty (choice)** Sets the degree to which T<sub>E</sub>X is discouraged from undertaking hyphenation, from the choices `low`, `medium` and `high`. Default: low

#### **Semantics & Comments:**

Determines both whether hyphenation is allowed at all, and if so to what degree it is discouraged. Setting `penalty` to `high` does not prevent hyphenation: this is only done if `enable` is set `false`.

### **3.13 The object type ‘justification’**

**Arg:**

#### **Semantics:**

Controls the nature of justification undertaken within the galley. The template applies from the point of use forward.

### **3.14 The template ‘std’ (object type justification)**

**Attributes:**

**end-skip (skip)** The skip inserted to fill the last line of a paragraph.

Default: 0 pt plus 1 fil

**fixed-word-spacing (boolean)** Determines whether inter-word spacing has a stretch component (for non-monospaced fonts).

Default: false

**indent-width (length)** The length of the indent inserted at the start of the first line of a new paragraph.

**left-skip (skip)** The skip between the left margin of the galley and the left edge of a paragraph.

Default: 0 pt

**right-skip (skip)** The skip between the right margin of the galley and the right edge of a paragraph.

Default: 0 pt

**start-skip (skip)** The skip inserted in addition to `indent-width` at the start of a paragraph.

Default: 0 pt

#### **Semantics & Comments:**

The `std` template for justification provides rubber lengths at the start and end of the paragraph and at each side of the paragraph. It also allows for both flexible and fixed inter-word spacing. The interaction between the settings is demonstrated in the selection of standard instances provided.

### 3.14.1 The instance ‘justified’ (template justification/std)

**Attribute values:**

**indent-width** 15 pt

**Layout description & Comments:**

Sets paragraphs fully-justified with the first line indented by 15 pt.

### 3.14.2 The instance ‘noindent’ (template justification/std)

**Attribute values:**

**end-skip** 15 pt plus 1 fil  
**indent-width** 0 pt

**Layout description & Comments:**

Sets paragraphs fully-justified with no indent for the first line. To ensure that paragraphs have some visual distinction, the **end-skip** is set to insert some space in all cases.

## 3.15 The template ‘single’ (object type justification)

**Attributes:**

**end-skip (skip)** The skip inserted to fill the last line of a paragraph.

Default: 0 pt plus 1 fil

**fixed-word-spacing (boolean)** Determines whether inter-word spacing has a stretch component (for non-monospaced fonts).  
Default: false

**indent-width (length)** The length of the indent inserted at the start of the first line of a new paragraph.

**left-skip (skip)** The skip between the left margin of the galley and the left edge of a paragraph.  
Default: 0 pt

**right-skip (skip)** The skip between the right margin of the galley and the right edge of a paragraph.  
Default: 0 pt

**start-skip (skip)** The skip inserted in addition to **indent-width** at the start of a paragraph.  
Default: 0 pt

**stretch-last-line (boolean)** Determines whether inter-word spacing in the last line is stretched. If **true**, the spacing in the last line is stretched in the same factor as that in the penultimate line.  
Default: false

### Semantics & Comments:

The `single` template for justification provides rubber lengths at the start and end of the paragraph and at each side of the paragraph. It also allows for both flexible and fixed inter-word spacing. The interaction between the settings is demonstrated in the selection of standard instances provided. The template applies only to a single paragraph.

#### 3.15.1 The instance ‘ragged-left’ (template `justification/std`)

##### Attribute values:

```
end-skip      0 pt
fixed-word-spacing
indent-width   0 pt
left-skip     0 pt plus 2 em
right-skip    0 pt
```

##### Layout description & Comments:

Typesets material with a ragged left margin such that hyphenation will still occur and such that very short lines are discouraged. This is similar to the L<sup>A</sup>T<sub>E</sub>X 2<sub>ε</sub> `ragged2e` `RaggedLeft` environment.

#### 3.15.2 The instance ‘ragged-right’ (template `justification/std`)

##### Attribute values:

```
end-skip      0 pt
fixed-word-spacing
indent-width   0 pt
left-skip     0 pt
right-skip    0 pt plus 2 em
```

##### Layout description & Comments:

Typesets material with a ragged right margin such that hyphenation will still occur and such that very short lines are discouraged. This is similar to the L<sup>A</sup>T<sub>E</sub>X 2<sub>ε</sub> `ragged2e` `RaggedLeft` environment.

#### 3.15.3 The instance ‘center’ (template `justification/std`)

##### Attribute values:

```
end-skip      0 pt
fixed-word-spacing
indent-width   0 pt
left-skip     0 pt plus 1 fil
right-skip    0 pt plus 1 fil
```

#### **Layout description & Comments:**

Centres typeset material such that hyphenation is discouraged and short lines are allowed.

### **3.16 The template ‘compound’ (object type justification)**

#### **Attributes:**

**first-paragraph** (instance) Justification for the first paragraph.

**other-paragraphs** (instance) Justification for the remaining paragraphs.

#### **Semantics & Comments:**

Here, both keys should themselves be instances of the `justification` template. The `compound` template is used to set up a single “non-standard” paragraph followed by “standard” ones. For example, it can be used to ensure that one `noindent` paragraph is then followed by `std` justification.

### **3.17 The object type ‘line-breaking’**

#### **Arg:**

#### **Semantics:**

Controls the line breaking attempted by T<sub>E</sub>X when typesetting material for the galley. This does not include whether words are hyphenated, which is handled separately.

### **3.18 The template ‘std’ (object type line-breaking)**

#### **Attributes:**

**badness** (integer) Boundary that if exceeded will cause T<sub>E</sub>X to report an underfull line. Default: 1000

**binop-penalty** (integer) Penalty charged if an inline math formula is broken at a binary operator. Default: 700

**double-hyphen-demerits** (integer) Extra demerit charge of two (or more) lines in succession end in a hyphen. Default: 10 000

**emergency-stretch** (skip) Additional stretch assumed for each line if no better line breaking can be found without it. This stretch is not actually added to lines, so its use may result in underfull box warnings. Default: 0 pt

**final-hyphen-demerits** (integer) Extra demerit charge if the second last line is hyphenated. Default: 5000

|                                    |  |                 |
|------------------------------------|--|-----------------|
| <b>fuzz (length)</b>               | Boundary below overfull lines are not reported.  | Default: 0.1 pt |
| <b>mismatch-demerits (integer)</b> | Extra demerit charge if two visually incompatible lines follow each other.   | Default: 10000  |
| <b>line-penalty (integer)</b>      | Extra penalty charged per line in the paragraph. By making this penalty higher T <sub>E</sub> X will try harder to produce compact paragraphs.                               | Default: 10     |
| <b>pretolerance (integer)</b>      | Maximum tolerance allowed for individual lines to break the paragraph without attempting hyphenation.  | Default: 100    |
| <b>relation-penalty (integer)</b>  | Penalty charged if an inline math formula is broken at a relational symbol.  | Default: 500    |
| <b>tolerance (integer)</b>         | Maximum tolerance allowed for individual lines when breaking a paragraph while attempting hyphenation (if this limit can't be met <b>emergency-stretch</b> comes into play). | Default: 200    |

#### Semantics & Comments:

This is an interface to the underlying T<sub>E</sub>X system for determining line breaking.

### 3.19 Between paragraphs

### 3.20 The object type ‘paragraph-breaking’

**Arg:**

#### Semantics:

This object type determines how T<sub>E</sub>X determines the behaviour when the paragraph-breaking algorithm is calculating whether to break up a paragraph. Thus for example an instance of this object type may prevent breaks within a paragraph, forbid widows or orphans, *etc.*

### 3.21 The template ‘std’ (object type paragraph-breaking)

#### Attributes:

|                          |  |               |
|--------------------------|--|---------------|
| <b>badness (integer)</b> | Boundary that if exceeded will cause T <sub>E</sub> X to report an underfull vertical box. | Default: 1000 |
|--------------------------|--|---------------|

|                                 |  |              |
|---------------------------------|--|--------------|
| <b>broken-penalty (integer)</b> | Penalty for page breaking after a hyphenated line. | Default: 100 |
|---------------------------------|--|--------------|

|                               |  |              |
|-------------------------------|--|--------------|
| <b>club-penalty (integer)</b> | Penalty for generating a club line when page breaking. | Default: 150 |
|-------------------------------|--|--------------|

**display-club-penalty (integer)** Penalty for breaking between to leave a club line after display math. Default: 150

**display-widow-penalty (integer)** Penalty for breaking between to leave a widow line before display math. Default: 150

**fuzz (length)** Boundary below which overfull vertical boxes are not reported. Default: 0.1 pt

**interline-penalty (integer)** Penalty for breaking between lines in a paragraph. Default: 0

**pre-display-penalty (integer)** Penalty for breaking between immediately before display math material. Default: 10 000

**post-display-penalty (integer)** Penalty for breaking between immediately after display math material. Default: 0

**widow-penalty (integer)** Penalty for generating a widow line when page breaking. Default: 150

#### **Semantics & Comments:**

This template provides an interface to the underlying T<sub>E</sub>X mechanism for controlling page breaking. The template applies on an ongoing basis to all paragraphs after the template is used.

#### **3.21.1 The instance ‘std’ (template paragraph-breaking/std)**

##### **Attribute values:**

##### **Layout description & Comments:**

Sets paragraphs such that they can break with widows and orphans discouraged but not prevented. Breaks are possible after display math material but no immediately before it.

#### **3.21.2 The instance ‘nobreak’ (template paragraph-breaking/std)**

##### **Attribute values:**

interline-penalty 0 000  
post-display-penalty 0 000

##### **Layout description & Comments:**

Sets paragraphs such that they cannot be broken at all (as far as is possible in T<sub>E</sub>X).

### 3.21.3 The instance ‘nolone’ (template paragraph-breaking/std)

Attribute values:

```
club-penalty 10 000
display-widow-penalty
widow-penalty 10 000
```

Layout description & Comments:

Sets paragraphs such that they cannot be broken to leave a club or widow line (as far as is possible in T<sub>E</sub>X).

## 3.22 The template ‘single’ (object type paragraph-breaking)

Attributes:

**badness (integer)** Boundary that if exceeded will cause T<sub>E</sub>X to report an underfull vertical box.  
Default: ⟨none⟩

**broken-penalty (integer)** Penalty for page breaking after a hyphenated line.  
Default: ⟨none⟩

**club-penalty (integer)** Penalty for generating a club line when page breaking.  
Default: ⟨none⟩

**display-club-penalty (integer)** Penalty for breaking between to leave a club line after display math.  
Default: ⟨none⟩

**display-widow-penalty (integer)** Penalty for breaking between to leave a widow line before display math.  
Default: ⟨none⟩

**fuzz (length)** Boundary below which overfull vertical boxes are not reported.  
Default: ⟨none⟩

**interline-penalty (integer)** Penalty for breaking between lines in a paragraph.  
Default: ⟨none⟩

**pre-display-penalty (integer)** Penalty for breaking between immediately before display math material.  
Default: ⟨none⟩

**post-display-penalty (integer)** Penalty for breaking between immediately after display math material.  
Default: ⟨none⟩

**widow-penalty (integer)** Penalty for generating a widow line when page breaking.  
Default: ⟨none⟩

#### **Semantics & Comments:**

This template provides an interface to the underlying T<sub>E</sub>X mechanism for controlling page breaking. The template applies only to the next paragraph, and can thus be used to achieve effects such as non-breaking paragraphs.

##### **3.22.1 The instance ‘single-std’ (template paragraph-breaking/single)**

###### **Attribute values:**

###### **Layout description & Comments:**

Sets the next paragraph such that it can break with widows and orphans discouraged but not prevented. Breaks are possible after display math material but no immediately before it.

##### **3.22.2 The instance ‘single-nobreak’ (template paragraph-breaking/single)**

###### **Attribute values:**

**interline-penalty** 10 000  
**post-display-penalty** 00

###### **Layout description & Comments:**

Sets the next paragraph such that it cannot be broken at all (as far as is possible in T<sub>E</sub>X).

##### **3.22.3 The instance ‘single-noclub’ (template paragraph-breaking/single)**

###### **Attribute values:**

**club-penalty** 10 000  
**display-club-penalty** 00

###### **Layout description & Comments:**

Sets the next paragraph such that it cannot be broken to leave a club line (as far as is possible in T<sub>E</sub>X).

##### **3.22.4 The instance ‘single-nolone’ (template paragraph-breaking/single)**

###### **Attribute values:**

**club-penalty** 10 000  
**display-club-penalty** 10 000  
**display-widow-penalty** 00  
**widow-penalty** 10 000

#### **Layout description & Comments:**

Sets the next paragraph such that it cannot be broken to leave a club or widow line (as far as is possible in  $\text{\TeX}$ ).

#### **3.22.5 The instance ‘single-nowidow’ (template paragraph-breaking/single)**

##### **Attribute values:**

```
display-widow-penalty
widow-penalty 10 000
```

#### **Layout description & Comments:**

Sets the next paragraph such that it cannot be broken to leave a widow line (as far as is possible in  $\text{\TeX}$ ).

## **4 xgalley Implementation**

This module provided a template-level interface for the L<sup>A</sup>T<sub>E</sub>X3 galley. As such, the code here is intended for design-level changes which apply to large blocks. The variables provided are therefore used only for supporting the templates, while any documented interfaces are in l3galley.

```
1 (*package)
2 (@@=galley)
3 \ProvidesExplPackage
4   {\ExplFileName}{\ExplFileDate}{\ExplFileVersion}{\ExplFileDescription}
5 \RequirePackage{xparse,xtemplate,l3galley}
```

### **4.1 Variables**

`\l_galley_tmpa_clist` Scratch space.

`\l_galley_tmpb_clist` 6 \clist\_new:N \l\_galley\_tmpa\_clist  
7 \clist\_new:N \l\_galley\_tmpb\_clist

*(End definition for \l\_galley\_tmpa\_clist and \l\_galley\_tmpb\_clist. These variables are documented on page ??.)*

## 4.2 Layer two: internal dimensions

There is a single object type for level two, the `measure` for the text in the galley. There are no arguments, as the measure is a design concept.

```
8 \DeclareObjectType { measure } { 0 }
```

There are two templates for galley measures: absolute and relative. Both use the same interface.

```
9 \DeclareTemplateInterface { measure } { absolute } { 0 }
10 {
11     left-margin : length = 0 pt ,
12     right-margin : length = 0 pt
13 }
14 \DeclareTemplateInterface { measure } { relative } { 0 }
15 {
16     left-margin : length = 0 pt ,
17     right-margin : length = 0 pt
18 }
```

`\l_galley_left_margin_dim` In the **absolute** template, the two margin values are relative to the edges of the galley.  
`\l_galley_right_margin_dim` This means that any existing offset or line-length adjustment are ignored.

```
19 (*package)
20 \cs_new_eq:NN \l_galley_left_margin_dim \leftmargin
21 
```

~~22 (\*package)~~
~~23 \cs\_new\_eq:NN \l\_galley\_right\_margin\_dim \rightmargin~~
~~24~~ 
~~25 \DeclareTemplateCode { measure } { absolute } { 0 }~~
~~26 {
27 left-margin = \l\_galley\_left\_margin\_dim ,
28 right-margin = \l\_galley\_right\_margin\_dim
29 }
30 {
31 \AssignTemplateKeys
32 \galley\_margins\_set\_absolute:nn \l\_galley\_left\_margin\_dim
33 \l\_galley\_right\_margin\_dim
34 }~~

On the other hand, the **relative** template works relative to the current indentation at both sides.

```
35 \DeclareTemplateCode { measure } { relative } { 0 }
36 {
37     left-margin = \l_galley_left_margin_dim ,
38     right-margin = \l_galley_right_margin_dim
39 }
40 {
41     \AssignTemplateKeys
42     \galley_margins_set_relative:nn \l_galley_left_margin_dim
43         \l_galley_right_margin_dim
44 }
```

(End definition for `\l_galley_left_margin_dim` and `\l_galley_right_margin_dim`. These variables are documented on page ??.)

### 4.3 Layer three: paragraph shape

The object type `parshape` is a somewhat extended interface to the TeX `\tex_parshape:D` primitive. As with the `measure`, the `parshape` template has no arguments as it is essentially a design-oriented concept.

```
45 \DeclareObjectType { parshape } { 0 }
```

There are two standard templates for paragraph shapes which do something, both with the same interface. The `hang` template provides one or more standard lines followed by a hanging paragraph, while the `initial` template cuts out a space at the start of the paragraph.

```
46 \DeclareTemplateInterface { parshape } { hang } { 0 }
47 {
48     indent      : length = 0 pt ,
49     on-left-side : boolean = true ,
50     lines       : integer = 1
51 }
52 \DeclareTemplateInterface { parshape } { initial } { 0 }
53 {
54     indent      : length = 0 pt ,
55     on-left-side : boolean = true ,
56     lines       : integer = 2
57 }
```

`\l_galley_parshape_indent_dim` Both of the templates are implemented as special cases of the more general function  
`\l_galley_parshape_on_left_bool`

```
58 \DeclareTemplateCode { parshape } { hang } { 0 }
59 {
60     indent      = \l_galley_parshape_indent_dim ,
61     on-left-side = \l_galley_parshape_on_left_bool ,
62     lines       = \l_galley_parshape_lines_int
63 }
64 {
65     \AssignTemplateKeys
66     \bool_if:NTF \l_galley_parshape_on_left_bool
67     {
68         \galley_parshape_set_single:nVVN
69             \l_galley_parshape_lines_int
70             \l_galley_parshape_indent_dim
71             \c_zero_dim
72             \c_false_bool
73     }
74 {
75     \galley_parshape_set_single:nVVN
76         \l_galley_parshape_lines_int
77         \c_zero_dim
```

```

78         \l_galley_parshape_indent_dim
79         \c_false_bool
80     }
81 }
82 \DeclareTemplateCode { parshape } { initial } { 0 }
83 {
84     indent      = \l_galley_parshape_indent_dim ,
85     on-left-side = \l_galley_parshape_on_left_bool ,
86     lines       = \l_galley_parshape_lines_int
87 }
88 {
89     \AssignTemplateKeys
90     \clist_clear:N \l_galley_tmpa_clist
91     \clist_clear:N \l_galley_tmrb_clist
92     \prg_replicate:nn { \l_galley_parshape_lines_int }
93     {
94         \clist_put_right:Nn \l_galley_tmpa_clist
95             { \l_galley_parshape_indent_dim }
96         \clist_put_right:Nn \l_galley_tmrb_clist
97             { \c_zero_dim }
98     }
99     \bool_if:NTF \l_galley_parshape_on_left_bool
100    {
101        \galley_parshape_set_single:nVVN
102            \c_zero
103            \l_galley_tmpa_clist
104            \l_galley_tmrb_clist
105            \c_true_bool
106    }
107    {
108        \galley_parshape_set_single:nVVN
109            \c_zero
110            \l_galley_tmrb_clist
111            \l_galley_tmpa_clist
112            \c_true_bool
113    }
114 }

```

(End definition for `\l_galley_parshape_indent_dim`. This function is documented on page ??.)

There is also a “do nothing” paragraph shape for cases where a template is needed but no action is desirable.

```

115 \DeclareTemplateInterface { parshape } { std } { 0 } { }
116 \DeclareTemplateCode { parshape } { std } { 0 } { } { }

```

#### 4.4 Layer four: formatting inside the paragraph

The first type of object within a paragraph is the hyphenation. This object needs no arguments.

```

117 \DeclareObjectType { hyphenation } { 0 }

```

There is only hyphenation template as standard. This provides a semi-flexible interface to the underlying TeX methods. (The detail is therefore hidden within the implementation phase.)

```

118 \DeclareTemplateInterface { hyphenation } { std } { 0 }
119   {
120     enable           : boolean          = true ,
121     enable-upper-case : boolean          = true ,
122     penalty          : choice { low , medium , high } = low
123   }

```

The implementation for hyphenation mainly sets low-level values. The minimum number of characters after a hyphen is set directly, whereas the number before is not. This is so that `\tex_lefthyphenmin:D` can also be used to completely prevent hyphenation.

```

124 \DeclareTemplateCode { hyphenation } { std } { 0 }
125   {
126     enable           = \l_galley_hyphen_enable_bool ,
127     enable-upper-case = \l_galley_hyphen_uppercase_bool ,
128     penalty          =
129       {
130         low      =
131           {
132             \int_set:Nn \tex_hyphenpenalty:D { 51 }
133             \int_set:Nn \tex_exhyphenpenalty:D { 51 }
134           } ,
135         medium =
136           {
137             \int_set:Nn \tex_hyphenpenalty:D { 151 }
138             \int_set:Nn \tex_exhyphenpenalty:D { 151 }
139           } ,
140         high    =
141           {
142             \int_set:Nn \tex_hyphenpenalty:D { 301 }
143             \int_set:Nn \tex_exhyphenpenalty:D { 301 }
144           } ,
145       }
146   }
147   {
148     \AssignTemplateKeys
149     \int_set:Nn \tex_lefthyphenmin:D
150       {
151         \bool_if:NTF \l_galley_hyphen_enable_bool
152           { \l_galley_hyphen_left_int }
153           { 63 }
154       }
155     \int_set:Nn \tex_uchyph:D
156       {
157         \bool_if:NTF \l_galley_hyphen_uppercase_bool
158           { 1 }
159           { 0 }
160       }

```

```
161 }
```

At this stage, the default hyphenation character should be set and hyphenation should be enabled.

```
162 \UseTemplate { hyphenation } { std } { }
163 \tex_defaulthyphenchar:D 45 \scan_stop:
```

\l\_galley\_justification\_other\_tl Used for the reset system for justification: using this token list means that there is no need to remove anything from \g\_galley\_restore\_running\_tl.

```
164 \tl_new:N \l_galley_justification_other_tl
```

(*End definition for \l\_galley\_justification\_other\_tl. This variable is documented on page ??.*)

The second level four object is the justification, which again takes no arguments.

```
165 \DeclareObjectType { justification } { 0 }
```

There are two templates here with the same interface: the standard one to apply from this point onward, and one which applies only to a single paragraph.

```
166 \DeclareTemplateInterface { justification } { std } { 0 }
167 {
168   end-skip          : skip    = 0 pt plus 1 fil ,
169   fixed-word-spacing : boolean = false           ,
170   indent-width      : length              ,
171   left-skip         : skip    = 0 pt           ,
172   right-skip        : skip    = 0 pt           ,
173   start-skip        : skip    = 0 pt           ,
174   stretch-last-line : boolean = false
175 }
176 \DeclareTemplateInterface { justification } { single } { 0 }
177 {
178   end-skip          : skip    = 0 pt plus 1 fil ,
179   fixed-word-spacing : boolean = false           ,
180   indent-width      : length              ,
181   left-skip         : skip    = 0 pt           ,
182   right-skip        : skip    = 0 pt           ,
183   start-skip        : skip    = 0 pt           ,
184   stretch-last-line : boolean = false
185 }
```

\l\_galley\_fixed\_spacing\_bool The implementation here is pretty simple as almost everything that goes on is a simple case of saving the settings, which are then applied either by TeX itself or the rest of the galley system.

```
186 \DeclareTemplateCode { justification } { std } { 0 }
187 {
188   end-skip          = \l_galley_par_end_skip      ,
189   fixed-word-spacing = \l_galley_fixed_spacing_bool ,
190   indent-width      = \l_galley_par_indent_dim     ,
191   left-skip         = \l_galley_line_left_skip    ,
192   right-skip        = \l_galley_line_right_skip   ,
193   start-skip        = \l_galley_par_begin_skip    ,
194   stretch-last-line = \l_galley_par_stretch_last_bool
```

```

195    }
196    {
197        \AssignTemplateKeys
198        \tl_clear:N \l__galley_justification_other_tl
199        \galley_interword_spacing_set:N \l_galley_fixed_spacing_bool
200        \bool_if:NTF \l_galley_par_stretch_last_bool
201            { \int_set_eq:NN \l_galley_last_line_fit_int \c_one_thousand }
202            { \int_zero:N \l_galley_last_line_fit_int }
203        \skip_set:Nn \@rightskip { \l_galley_line_right_skip }
204    }
(End definition for \l_galley_fixed_spacing_bool. This variable is documented on page ??.)
To deal with a single paragraph, the approach used is to save the current settings to
the paragraph-reset code, then to assign the template in the same way as for the std
template.
205 \DeclareTemplateCode { justification } { single } { 0 }
206 {
207     end-skip          = \l_galley_par_end_skip      ,
208     fixed-word-spacing = \l_galley_fixed_spacing_bool ,
209     indent-width       = \l_galley_par_indent_dim      ,
210     left-skip          = \l_galley_line_left_skip      ,
211     right-skip         = \l_galley_line_right_skip     ,
212     start-skip         = \l_galley_par_begin_skip      ,
213     stretch-last-line  = \l_galley_par_stretch_last_bool
214 }
215 {
216     \tl_put_left:Nx \l__galley_justification_other_tl
217     {
218         \skip_set:Nn \exp_not:N \l_galley_par_end_skip
219             { \skip_use:N \l_galley_par_end_skip }
220         \bool_if:NTF \l_galley_fixed_spacing_bool
221             { \bool_set_true:N \exp_not:N \l_galley_fixed_spacing_bool }
222             { \bool_set_false:N \exp_not:N \l_galley_fixed_spacing_bool }
223         \galley_interword_spacing_set:N
224             \exp_not:N \l_galley_fixed_spacing_bool
225         \dim_set:Nn \exp_not:N \l_galley_par_indent_dim
226             { \dim_use:N \l_galley_par_indent_dim }
227         \skip_set:Nn \l_galley_line_left_skip
228             { \skip_use:N \l_galley_line_left_skip }
229         \skip_set:Nn \exp_not:N \l_galley_line_right_skip
230             { \skip_use:N \l_galley_line_right_skip }
231         \skip_set:Nn \exp_not:N \l_galley_par_begin_skip
232             { \skip_use:N \l_galley_par_begin_skip }
233         \int_set:Nn \exp_not:N \l_galley_last_line_fit_int
234             { \int_use:N \l_galley_last_line_fit_int }
235         \skip_set:Nn \exp_not:N \@rightskip
236             { \skip_use:N \l_galley_line_right_skip }
237     }
238     \tl_gput_right:Nn \g_galley_restore_running_tl
239     { \l__galley_justification_other_tl }

```

```

240   \AssignTemplateKeys
241   \galley_interword_spacing_set:N \l_galley_fixed_spacing_bool
242   \bool_if:NTF \l_galley_par_stretch_last_bool
243     { \int_set_eq:NN \l_galley_last_line_fit_int \c_one_thousand }
244     { \int_zero:N \l_galley_last_line_fit_int }
245   \skip_set:Nn \@rightskip { \l_galley_line_right_skip }
246 }
```

The standard instance for justification is very simple to set up as the default values for the template are set up for exactly this case. The advantage of this scheme is that at a design level altering the indent used for justified paragraphs is very easy to do. As this is the standard template for all L<sup>A</sup>T<sub>E</sub>X3 documents, it is applied here.

```

247 \DeclareInstance { justification } { justified } { std }
248   { indent-width = 15 pt }
249 \UseInstance { justification } { justified }
```

The instance for no indentation at all but with justified text is intended for layouts which leave white space between paragraphs. With no indentation, some space has to be included at the end of each paragraph. This is set up to mirror the indent that has been removed.

```

250 \DeclareInstance { justification } { noindent } { std }
251   {
252     end-skip      = 15 pt plus 1 fil ,
253     indent-width = 0 pt
254 }
```

The other standard justification schemes are for text which is ragged. The settings here are taken from the L<sup>A</sup>T<sub>E</sub>X 2 <sub>$\epsilon$</sub>  `ragged2e` package, as they maintain a reasonable appearance by ensuring that T<sub>E</sub>X will not be too tolerant of very short lines. To keep the design clear here, no default values are relied on even though this would make the instance declarations shorter.

```

255 \DeclareInstance { justification } { ragged-left } { std }
256   {
257     end-skip        = 0 pt           ,
258     fixed-word-spacing = true       ,
259     indent-width     = 0 pt           ,
260     left-skip       = 0 pt plus 2 em ,
261     right-skip      = 0 pt
262   }
263 \DeclareInstance { justification } { ragged-right } { std }
264   {
265     end-skip        = 0 pt plus 1 fil ,
266     fixed-word-spacing = true       ,
267     indent-width     = 0 pt           ,
268     left-skip       = 0 pt           ,
269     right-skip      = 0 pt plus 2 em
270 }
```

The `center` instance is used to center material with minimal hyphenation.

```

271 \DeclareInstance { justification } { center } { std }
```

```

272  {
273      end-skip          = 0 pt           ,
274      fixed-word-spacing = true          ,
275      indent-width      = 0 pt           ,
276      left-skip         = 0 pt plus 1 fil ,
277      right-skip        = 0 pt plus 1 fil
278  }

```

`\_galley_justification_first:` A second form of justification template is the case where the first paragraph is different from all of the others. This is set up by getting the justification to reset itself after the first paragraph. The code built into the `std` version will ensure that any subsequent template use will over-ride the setting here correctly.

```

279 \DeclareTemplateInterface { justification } { compound } { 0 }
280  {
281      first-paragraph : instance { justification } ,
282      other-paragraphs : instance { justification }
283  }
284 \DeclareTemplateCode { justification } { compound } { 0 }
285  {
286      first-paragraph = \_galley_justification_first: ,
287      other-paragraphs = \_galley_justification_other:
288  }
289  {
290      \AssignTemplateKeys
291      \_galley_justification_first:
292      \tl_set:Nn \l_galley_justification_other_tl
293      { \_galley_justification_other: }
294      \tl_gput_right:Nn \g_galley_restore_running_tl
295      { \l_galley_justification_other_tl }
296  }

```

(End definition for `\_galley_justification_first:` and `\_galley_justification_other:`. These functions are documented on page ??.)

How `TeX` breaks text into lines is influenced by a number of parameters, most of which are not actually likely to change. These work with the `hyphenation` but are independent of whether any hyphenation is actually active. The math values here could be set up as a separate template, but in practice this seems likely to be overkill.

```
297 \DeclareObjectType { line-breaking } { 0 }
```

The only template provided for line breaking is a simple interface to `TeX`'s parameters. There is not really much that can be added to this: after all, the way that penalties work is more or less arbitrary but works well! The default values given here are intended to be sensible for a lot of cases.

```

298 \DeclareTemplateInterface { line-breaking } { std } { 0 }
299  {
300      badness           : integer = 1000   ,
301      binop-penalty     : integer = 700    ,
302      double-hyphen-demerits : integer = 10 000 ,
303      emergency-stretch   : skip    = 0 pt   ,
304      final-hyphen-demerits : integer = 5000   ,

```

```

305     fuzz          : length  = 0.1 pt ,
306     line-penalty   : integer = 10      ,
307     mismatch-demerits : integer = 10 000 ,
308     pretolerance   : integer = 100     ,
309     relation-penalty : integer = 500     ,
310     tolerance       : integer = 200
311   }
312 \DeclareTemplateCode{ line-breaking } { std } { 0 }
313   {
314     badness          = \l_galley_linebreak_badness_int      ,
315     binop-penalty    = \l_galley_binop_penalty_int        ,
316     double-hyphen-demerits = \l_galley_double_hyphen_demerits_int ,
317     emergency-stretch = \l_galley_emergency_stretch_skip    ,
318     final-hyphen-demerits = \l_galley_final_hyphen_demerits_int ,
319     fuzz             = \l_galley_linebreak_fuzz_dim        ,
320     line-penalty     = \l_galley_linebreak_penalty_int      ,
321     mismatch-demerits = \l_galley_mismatch_demerits_int    ,
322     pretolerance     = \l_galley_linebreak_pretolerance_int ,
323     relation-penalty = \l_galley_relation_penalty_int      ,
324     tolerance        = \l_galley_linebreak_tolerance_int
325   }
326 { \AssignTemplateKeys }

```

The default values are set such that they are suitable for good quality typesetting. So the standard template changes nothing at all from the template. This instance should also be applied now, as it will then apply to the entire document unless changed deliberately.

```

327 \DeclareInstance { line-breaking } { std } { std } { }
328 \UseInstance { line-breaking } { std }

```

## 4.5 Between paragraphs

The second object here sets up how TeX acts to break paragraphs at page boundaries. As with the `line-breaking` object, there is not much to do except provide an interface to the TeX internals. The `std` template does *not* make the  $\varepsilon$ -TeX array nature of various penalties available.

```

\l_galley_club_penalty_int
  \l_galley_display_club_penalty_int
  \l_galley_display_widow_penalty_int
  \l_galley_interline_penalty_int
\l_galley_widow_penalty_int
329 \DeclareObjectType { paragraph-breaking } { 0 }
330 \DeclareTemplateInterface { paragraph-breaking } { std } { 0 }
331   {
332     badness          : integer = 1000     ,
333     broken-penalty   : integer = 100      ,
334     club-penalty     : integer = 150      ,
335     display-club-penalty : integer = 150    ,
336     display-widow-penalty : integer = 150    ,
337     fuzz             : length  = 0.1 pt ,
338     interline-penalty : integer = 0       ,
339     post-display-penalty : integer = 0       ,
340     pre-display-penalty : integer = 10 000 ,
341     widow-penalty    : integer = 150
342   }

```

```

343 \DeclareTemplateCode { paragraph-breaking } { std } { 0 }
344 {
345     badness          = \l_galley_parbreak_badness_int      ,
346     broken-penalty   = \l_galley_broken_penalty_int       ,
347     club-penalty     = \l_galley_club_penalty_int        ,
348     display-club-penalty = \l_galley_display_club_penalty_int ,
349     display-widow-penalty = \l_galley_display_widow_penalty_int ,
350     fuzz             = \l_galley_parbreak_fuzz_dim        ,
351     interline-penalty = \l_galley_interline_penalty_int   ,
352     post-display-penalty = \l_galley_post_display_penalty_int ,
353     pre-display-penalty = \l_galley_pre_display_penalty_int ,
354     widow-penalty    = \l_galley_widow_penalty_int
355 }
356 {
357     \AssignTemplateKeys
358     \galley_club_penalties_set:V           \l_galley_club_penalty_int
359     \galley_display_club_penalties_set:V   \l_galley_display_club_penalty_int
360     \galley_display_widow_penalties_set:V  \l_galley_display_widow_penalty_int
361     \galley_interline_penalty_set:n       \l_galley_interline_penalty_int
362     \galley_widow_penalties_set:V         \l_galley_widow_penalty_int
363 }
(End definition for \l_galley_club_penalty_int and others. These variables are documented on page ??.)

```

The standard instance of the `paragraph-breaking` object simply applies the defaults: this is used.

```

364 \DeclareInstance { paragraph-breaking } { std } { std } { }
365 \UseInstance { paragraph-breaking } { std }

```

Two additional instances are provided: one to prevent any breaks at all, and a second to prevent any widow or club lines.

```

366 \DeclareInstance { paragraph-breaking } { nobreak } { std }
367 {
368     interline-penalty = 10 000 ,
369     post-display-penalty = 10 000
370 }
371 \DeclareInstance { paragraph-breaking } { nolone } { std }
372 {
373     club-penalty      = 10 000 ,
374     display-club-penalty = 10 000 ,
375     display-widow-penalty = 10 000 ,
376     widow-penalty     = 10 000
377 }

```

There is also a version of this code which applies only to one paragraph. This is done by storing the input in token list variables with no default: only explicit settings will be picked up.

```

378 \DeclareTemplateInterface { paragraph-breaking } { single } { 0 }
379 {
380     badness          : tokenlist ,

```

```

381     broken-penalty      : tokenlist ,
382     club-penalty        : tokenlist ,
383     display-club-penalty : tokenlist ,
384     display-widow-penalty : tokenlist ,
385     fuzz                 : tokenlist ,
386     interline-penalty    : tokenlist ,
387     post-display-penalty : tokenlist ,
388     pre-display-penalty  : tokenlist ,
389     widow-penalty       : tokenlist
390   }
391 \DeclareTemplateCode { paragraph-breaking } { single } { 0 }
392   {
393     badness            = \l__galley_parbreak_badness_tl ,
394     broken-penalty    = \l__galley_broken_penalty_tl ,
395     club-penalty      = \l__galley_club_penalties_tl ,
396     display-club-penalty = \l__galley_display_club_penalties_tl ,
397     display-widow-penalty = \l__galley_display_widow_penalties_tl ,
398     fuzz               = \l__galley_parbreak_fuzz_tl ,
399     interline-penalty  = \l__galley_interline_penalty_tl ,
400     post-display-penalty = \l__galley_post_display_penalty_tl ,
401     pre-display-penalty = \l__galley_pre_display_penalty_tl ,
402     widow-penalty     = \l__galley_widow_penalties_tl
403   }
404   {
405     \AssignTemplateKeys

```

The fuzz and interline penalties are handled explicitly as they have particular requirements.

```

406   \tl_if_empty:NF \l__galley_interline_penalty_tl
407   {
408     \tl_gput_right:Nx \g_galley_par_reset_hook_tl
409     {
410       \int_set:Nn \exp_not:N \l__galley_interline_penalty_int
411       { \galley_interline_penalty: }
412     }
413     \int_set:Nn \l__galley_interline_penalty_int
414     { \l__galley_interline_penalty_tl }
415   }
416 \tl_if_empty:NF \l__galley_parbreak_fuzz_tl
417   {
418     \tl_gput_right:Nx \g_galley_par_reset_hook_tl
419     {
420       \dim_set:Nn \exp_not:N \l_galley_parbreak_fuzz_dim
421       { \dim_use:N \l_galley_parbreak_fuzz_dim }
422     }
423     \dim_set:Nn \l_galley_parbreak_fuzz_dim { \l__galley_parbreak_fuzz_tl }
424   }

```

For the single integer penalties, a simple check is needed to save the value.

```
425   \seq_map_inline:Nn \c_galley_parbreak_single_seq
```

```

426    {
427        \tl_if_empty:cF { l_galley_ ##1 _tl }
428        {
429            \tl_gput_right:Nx \g_galley_par_reset_hook_tl
430            {
431                \int_set:Nn \exp_not:c { l_galley_ ##1 _int }
432                { \int_use:c { l_galley_ ##1 _int } }
433            }
434            \int_set:cn { l_galley_ ##1 _int }
435            { \tl_use:c { l_galley_ ##1 _tl } }
436        }
437    }

```

A bit more complex for the array penalties. Although the interface here does not expose the arrays, it is necessary to correctly save them.

```

438     \seq_map_inline:Nn \c__galley_parbreak_multi_seq
439     {
440         \tl_if_empty:cF { l_galley_ ##1 _tl }
441         {
442             \use:c { galley_save_ ##1 :N } \l__galley_tmpa_clist
443             \tl_gput_right:Nx \g_galley_par_reset_hook_tl
444             {
445                 \exp_not:c { galley_set_ ##1 :n }
446                 { \exp_not:o \l__galley_tmpa_clist }
447             }
448             \use:c { galley_set_ ##1 :v } { l_galley_ ##1 _tl }
449         }
450     }
451 }
452 \seq_new:N \c__galley_parbreak_multi_seq
453 \seq_gput_right:Nn \c__galley_parbreak_multi_seq { club_penalties }
454 \seq_gput_right:Nn \c__galley_parbreak_multi_seq { display_club_penalties }
455 \seq_gput_right:Nn \c__galley_parbreak_multi_seq { display_widow_penalties }
456 \seq_gput_right:Nn \c__galley_parbreak_multi_seq { widow_penalties }
457 \seq_new:N \c__galley_parbreak_single_seq
458 \seq_gput_right:Nn \c__galley_parbreak_single_seq { parbreak_badness }
459 \seq_gput_right:Nn \c__galley_parbreak_single_seq { broken_penalty }
460 \seq_gput_right:Nn \c__galley_parbreak_single_seq { post_display_penalty }
461 \seq_gput_right:Nn \c__galley_parbreak_single_seq { pre_display_penalty }
(End definition for \l__galley_parbreak_badness_t1 and others. These variables are documented on page ??.)
462 \DeclareInstance { paragraph-breaking } { single-std } { single } { }
463 \DeclareInstance { paragraph-breaking } { single-nobreak } { single }
464 {
465     interline-penalty = 10 000 ,
466     post-display-penalty = 10 000
467 }
468 \DeclareInstance { paragraph-breaking } { single-noclub } { single }
469 {
470     club-penalty = 10 000 ,

```

```

471     display-club-penalty = 10 000
472   }
473 \DeclareInstance { paragraph-breaking } { single-nolone } { single }
474   {
475     club-penalty      = 10 000 ,
476     display-club-penalty = 10 000 ,
477     display-widow-penalty = 10 000 ,
478     widow-penalty      = 10 000
479   }
480 \DeclareInstance { paragraph-breaking } { single-nowidow } { single }
481   {
482     display-widow-penalty = 10 000 ,
483     widow-penalty      = 10 000
484 }
```

## 4.6 Templates for display material

To allow special handling of display-like material, templates are needed at the beginning and end of the block which set up any special space or breaks. These need to be optional, and so are stored as token lists: rather than “magic” values, empty lists indicate that standard settings are to be used. To ensure that the error checking needed takes place early, each token list is re-set with the appropriate evaluation.

```

485 \DeclareObjectType { display-begin } { 0 }
486 \DeclareObjectType { display-end } { 0 }
487 \DeclareTemplateInterface { display-begin } { std } { 0 }
488   {
489     par-penalty : tokenlist ,
490     par-space  : tokenlist ,
491     penalty    : tokenlist ,
492     space      : tokenlist
493   }
494 \DeclareTemplateInterface { display-end } { std } { 0 }
495   {
496     par-penalty : tokenlist ,
497     par-space  : tokenlist ,
498     penalty    : tokenlist ,
499     space      : tokenlist
500   }
501 \DeclareTemplateCode { display-begin } { std } { 0 }
502   {
503     par-penalty = \l_galley_display_begin_par_vpenalty_tl ,
504     par-space  = \l_galley_display_begin_par_vspace_tl ,
505     penalty    = \l_galley_display_begin_vpenalty_tl ,
506     space      = \l_galley_display_begin_vspace_tl
507   }
508   {
509     \AssignTemplateKeys
510     \tl_if_empty:NF \l_galley_display_begin_par_vpenalty_tl
511     {
```

```

512     \tl_set:Nx \l_galley_display_begin_par_vpenalty_tl
513         { \int_eval:n { \l_galley_display_begin_par_vpenalty_tl } }
514     }
515 \tl_if_empty:NF \l_galley_display_begin_par_vspace_tl
516     {
517         \tl_set:Nx \l_galley_display_begin_par_vspace_tl
518             { \skip_eval:n { \l_galley_display_begin_par_vspace_tl } }
519     }
520 \tl_if_empty:NF \l_galley_display_begin_vpenalty_tl
521     {
522         \tl_set:Nx \l_galley_display_begin_vpenalty_tl
523             { \int_eval:n { \l_galley_display_begin_vpenalty_tl } }
524     }
525 \tl_if_empty:NF \l_galley_display_begin_vspace_tl
526     {
527         \tl_set:Nx \l_galley_display_begin_vspace_tl
528             { \skip_eval:n { \l_galley_display_begin_vspace_tl } }
529     }
530 }
531 \DeclareTemplateCode { display-end } { std } { 0 }
532 {
533     par-penalty = \l_galley_display_end_par_vpenalty_tl ,
534     par-space   = \l_galley_display_end_par_vspace_tl ,
535     penalty     = \l_galley_display_end_vpenalty_tl ,
536     space       = \l_galley_display_end_vspace_tl
537 }
538 {
539     \AssignTemplateKeys
540     \tl_if_empty:NF \l_galley_display_end_par_vpenalty_tl
541     {
542         \tl_set:Nx \l_galley_display_end_par_vpenalty_tl
543             { \int_eval:n { \l_galley_display_end_par_vpenalty_tl } }
544     }
545     \tl_if_empty:NF \l_galley_display_end_par_vspace_tl
546     {
547         \tl_set:Nx \l_galley_display_end_par_vspace_tl
548             { \skip_eval:n { \l_galley_display_end_par_vspace_tl } }
549     }
550     \tl_if_empty:NF \l_galley_display_end_vpenalty_tl
551     {
552         \tl_set:Nx \l_galley_display_end_vpenalty_tl
553             { \int_eval:n { \l_galley_display_end_vpenalty_tl } }
554     }
555     \tl_if_empty:NF \l_galley_display_end_vspace_tl
556     {
557         \tl_set:Nx \l_galley_display_end_vspace_tl
558             { \skip_eval:n { \l_galley_display_end_vspace_tl } }
559     }
560 }

```

## Index

The italic numbers denote the pages where the corresponding entry is described, numbers underlined point to the definition, all others indicate the places where it is used.

```

\int_set_eq:NN ..... 201, 243 \l_galley_widow_penalty_int ..... 329, 354, 362
\int_use:c ..... 432 ..... 329, 354, 362
\int_use:N ..... 234 \l_galley_display_begin_par_vpenalty_tl
\int_zero:N ..... 202, 244 ..... 503, 510, 512, 513
\l_galley_display_begin_par_vspace_tl
\l_galley_binop_penalty_int ..... 315 ..... 504, 515, 517, 518
\l_galley_broken_penalty_int ..... 346 ..... 505, 520, 522, 523
\l_galley_broken_penalty_tl .. 378, 394 \l_galley_display_begin_vspace_tl ...
\l_galley_club_penalties_tl .. 378, 395 ..... 506, 525, 527, 528
\l_galley_club_penalty_int 329, 347, 358 \l_galley_display_end_par_vpenalty_tl
\l_galley_display_club_penalties_tl ..... 533, 540, 542, 543
..... 378, 396 \l_galley_display_end_par_vspace_tl
\l_galley_display_club_penalty_int ..... 534, 545, 547, 548
..... 329, 348, 359 \l_galley_display_end_vpenalty_tl ...
\l_galley_display_widow_penalties_tl ..... 535, 550, 552, 553
..... 378, 397 \l_galley_display_end_vspace_tl ...
\l_galley_display_widow_penalty_int ..... 536, 555, 557, 558
..... 329, 349, 360 \l_galley_double_hyphen_demerits_int
\l_galley_interline_penalty_int ... ..... 316
..... 329, 351, 361, 410, 413 \l_galley_emergency_stretch_skip ...
\l_galley_interline_penalty_tl ..... 317
..... 378, 399, 406, 414 \l_galley_final_hyphen_demerits_int 318
\l_galley_justification_other_tl ... \l_galley_fixed_spacing_bool ...
..... 164, 164, 198, 216, 239, 292, 295 ..... 186,
\l_galley_left_margin_dim ..... 189, 199, 208, 220, 221, 222, 224, 241
..... 19, 20, 27, 32, 37, 42 \l_galley_hyphen_enable_bool ...
\l_galley_linebreak_penalty_int .. 320 \l_galley_hyphen_left_int ...
\l_galley_parbreak_badness_tl 378, 393 \l_galley_hyphen_uppercase_bool 127, 157
\l_galley_parbreak_fuzz_tl ..... \l_galley_last_line_fit_int ...
..... 378, 398, 416, 423 ..... 201, 202, 233, 234, 243, 244
\l_galley_parshape_indent_dim ..... \l_galley_line_left_skip ...
..... 58, 60, 70, 78, 84, 95 ..... 191, 210, 227, 228
\l_galley_parshape_lines_int ..... \l_galley_line_right_skip ...
..... 58, 62, 69, 76, 86, 92 ..... 192, 203, 211, 229, 230, 236, 245
\l_galley_parshape_on_left_bool ... \l_galley_linebreak_badness_int ...
..... 58, 61, 66, 85, 99 \l_galley_linebreak_fuzz_dim ...
\l_galley_post_display_penalty_int 352 \l_galley_linebreak_pretolerance_int ...
\l_galley_post_display_penalty_tl ..... 322
..... 378, 400 \l_galley_linebreak_tolerance_int ...
\l_galley_pre_display_penalty_int 353 \l_galley_mismatch_demerits_int ...
\l_galley_pre_display_penalty_tl ..... 324
..... 378, 401 \l_galley_par_begin_skip ...
\l_galley_relation_penalty_int ... 193, 212, 231, 232
\l_galley_right_margin_dim ..... \l_galley_par_end_skip 188, 207, 218, 219
..... 19, 23, 28, 33, 38, 43 \l_galley_par_indent_dim ...
\l_galley_tmpa_clist ..... ..... 190, 209, 225, 226
..... 6, 6, 90, 94, 103, 111, 442, 446 \l_galley_par_stretch_last_bool ...
\l_galley_tmpb_clist 6, 7, 91, 96, 104, 110 ..... 194, 200, 213, 242
\l_galley_widow_penalties_tl . 378, 402 \l_galley_parbreak_badness_int ...
..... 345
\l_galley_parbreak_fuzz_dim ..... 350, 420, 421, 423
\leftmargin ..... 20

```

|                          |  |
|--------------------------|--|
| <b>P</b>                 |  |
| \prg_replicate:nn        | 92                                     |
| \ProvidesExplPackage     | 3                                      |
| <b>R</b>                 |  |
| \RequirePackage          | 5                                      |
| \rightmargin             | 23                                     |
| <b>S</b>                 |  |
| \scan_stop:              | 163                                    |
| \seq_gput_right:Nn       | 453, 454, 455, 456, 458, 459, 460, 461 |
| \seq_map_inline:Nn       | 425, 438                               |
| \seq_new:N               | 452, 457                               |
| \skip_eval:n             | 518, 528, 548, 558                     |
| \skip_set:Nn             | 203, 218, 227, 229, 231, 235, 245      |
| \skip_use:N              | 219, 228, 230, 232, 236                |
| <b>T</b>                 |  |
| \tex_defaulthyphenchar:D | 163                                    |
| \tex_exhyphenpenalty:D   | 133, 138, 143                          |
| <b>U</b>                 |  |
| \use:c                   | 442, 448                               |
| \UseInstance             | 249, 328, 365                          |
| \UseTemplate             | 162                                    |